EXECUTION PANEL WITH AN OPTIONAL RISK-RULES LAYER

Fuse Trader Pro

Setup & User Guide

Everything you need to install, activate and use the panel — from import to your first trade.

Version 1.6 · Guide rev. 1.6.0

NinjaTrader 8 Compatible

Futures trading involves substantial risk of loss. See the Risk Disclosure on the last page.

NinjaTrader® is a registered trademark of NinjaTrader Group, LLC. No NinjaTrader company has any affiliation with the owner, developer, or provider of the products or services described herein, or any interest, ownership or otherwise, in any such product or service, or endorses, recommends or approves any such product or service.

CHANGELOG

What's new in 1.6.0

Re-import the add-on to update — see **Step 1** on page 04. Your license stays active and your presets and locks carry over. Version 1.6.0 also contains the changes of 1.5.1–1.5.3, which were not published separately.

New in 1.6.0 · One-click trial

- **7-day Pro trial with one click**
  No license key yet? Press **Start 7-day Pro trial** and every Pro feature unlocks right away — no email, no license key, no card. It ends on day 7 at 17:00 US Eastern. See page 08.
- **Welcome window**
  Shown once on a new computer: **Start 7-day Pro trial**, **I have a license key** or **Maybe later**. Maybe later is final; you can still start the trial later in Settings → About & License.
- **One edition per chart window**
  Fuse Trader Free and Fuse Trader Pro cannot be in the same chart window, not even on different tabs. In separate chart windows they work side by side. See page 11.
- **A paid license key takes over from the trial**
  When you activate a paid license key during the trial, the panel switches to the paid license. If you remove the paid key while the trial still runs, the trial continues with its remaining time. See page 09.
- **Trial end message**
  After the trial you can still close and manage open positions; new entries are off. The message says that Fuse Trader Free stays yours, and **Get lifetime license** opens the Fuse Trader card on fuseindicators.com.

Also in 1.6.0 (from 1.5.1–1.5.3)

- **Safety pop-up · Breakeven and SL never leave you without a stop**
  If a new stop price is already past the market, the position is closed instead of being left without protection. Fuse Trader tells you in a pop-up that does not block trading, also written to the NinjaTrader Alerts window with a sound. See page 16.
- **Request license key from the panel**
  Settings → About & License → Request license key sends the email you used at purchase together with your Machine ID. See page 06.
- **P&L from the last traded price · dollar value in previews**
  The panel P&L follows the last traded price, so it matches NinjaTrader's own Chart Trader more closely. Click and drag previews show risk and target in dollars. See page 13.

UPGRADING FROM 1.5.X

Tools → Import → NinjaScript Add-On... the new **FuseTrader_Pro.zip**, then restart NinjaTrader once so compilation finishes. Your existing license key, and a running trial key, keep working.

Futures trading involves substantial risk of loss. Past performance is not necessarily indicative of future results.

WELCOME

Before you start

Fuse Trader Pro is an **execution and position-management panel** for NinjaTrader 8. It provides one-click order entry, draggable stop/target brackets, bracket presets and an **optional layer of risk rules** that you define and the panel applies for you. This guide walks you through installation, activation, and every function of the panel.

What you need

Platform	NinjaTrader 8 (latest stable release recommended). Works on live and simulation accounts with data feeds supported by NinjaTrader 8.
Operating system	Windows 10 / 11. On Apple Silicon Macs, run NinjaTrader inside a Windows VM (Parallels / VMware) — the panel behaves identically.
Your license	The .zip add-on you downloaded, plus a lifetime license key (Step 3) — or start the free 7-day trial with one click in the panel, no key needed (page 08).

NinjaTrader® is a registered trademark of NinjaTrader Group, LLC. No NinjaTrader company has any affiliation with the owner, developer, or provider of the products or services described herein, or any interest, ownership or otherwise, in any such product or service, or endorses, recommends or approves any such product or service.

What's inside the download

A single NinjaScript add-on archive (**FuseTrader_Pro.zip**) containing the panel, plus this guide. You do **not** need to unzip it — NinjaTrader imports the archive directly.

THE 3-STEP SETUP

1 · Import the add-on → **2 · Add** the panel to a chart → **3 · Activate** with your license key, or start the 7-day trial. Roughly five minutes, once.

IMPORTANT · USING FUSE TRADER FREE TOO?

Fuse Trader Free and Fuse Trader Pro **cannot be in the same chart window** — not even on different tabs of it. Use a separate chart window for each (page 11).

A NOTE ON PRIVACY & SAFETY


Your license is tied to your computer's Machine ID; the license check and the trial run offline. The panel does not send your trading or account data anywhere. It goes online only to download the economic calendar (page 22) and, when you click **Send activation request**, to send your email address and Machine ID to Fuse Indicators. Keep your license key private.

Futures trading involves substantial risk of loss. Past performance is not necessarily indicative of future results.

STEP ONE

1 Import the add-on

In NinjaTrader, open the Control Center and go to **Tools → Import → NinjaScript Add-On...**




Tools → Import → NinjaScript Add-On... in the NinjaTrader Control Center
Simulated account.

1 Select the archive

A Windows file window opens. Browse to your downloaded **FuseTrader_Pro.zip** and select it. Import starts immediately — you don't unzip it first.

2 Confirmation

NinjaTrader imports and compiles the add-on automatically, then confirms:



Success — **"NinjaTrader successfully imported all scripts"**. Click OK.
Simulated account.

IMPORTANT


No manual compiling is required. If Fuse Trader Pro doesn't appear in the indicator list yet, simply restart NinjaTrader once — compilation finishes on startup.

Futures trading involves substantial risk of loss. Past performance is not necessarily indicative of future results.

STEP TWO

2 Add the panel to a chart

Open a chart for the instrument you trade (e.g. **NQ** or **MNQ**). Right-click the chart and choose **Indicators...**, then expand the **FuseSuite** folder and add **FuseTrader_Pro**.



FuseSuite → **FuseTrader_Pro** — the panel docks on the right of your chart

1. **Open Indicators**
   Right-click chart → **Indicators...**
2. **Pick Fuse Trader Pro**
   Under **FuseSuite**, double-click **FuseTrader_Pro** — it moves to Configured.
3. **Apply**
   Click **OK**. The panel appears docked to the right edge of the chart.

TIP

Save it to your workspace / chart template so the panel loads automatically every time you open that chart.

IMPORTANT · ONE EDITION PER CHART WINDOW

If **Fuse Trader Free** is in this chart window — on any of its tabs — Fuse Trader Pro does not start there and shows the notice **"Fuse Trader Free is already in this chart window."** Remove Free from that window (all of its tabs) and add Pro again, or put Pro in a different chart window. In separate chart windows, Free and Pro work side by side. See page 11.


Without a license key, the first time the panel loads on a new computer it shows the **Welcome to Fuse Trader Pro** window — start the free trial or enter your key (next page).

Futures trading involves substantial risk of loss. Past performance is not necessarily indicative of future results.

STEP THREE

3 Start the trial or activate

Without a license key the panel runs **locked**: it shows **"No license key entered"** and entries are disabled. The first time the panel loads on a new computer, the **Welcome to Fuse Trader Pro** window opens with three choices.



The welcome window — shown once on a new computer

Start 7-day Pro trial	Unlocks every Pro feature right away on this chart — no email, no license key, no card. A short message confirms the start and the end time (page 08).
I have a license key	Opens **Settings** → **About & License**, where you request, paste and activate your key (next page).
Maybe later	Closes the window. It is not shown again on this computer — you can start the trial any time later in **Settings** → **About & License**.

THE TRIAL NEVER STARTS BY ITSELF


Only a click starts it. While the trial is still available, clicking a locked entry button opens this window again, so you can start the trial or enter your key. The window also reminds you that Fuse Trader Free and Fuse Trader Pro cannot share one chart window (page 11).

Futures trading involves substantial risk of loss. Past performance is not necessarily indicative of future results.

STEP THREE · LICENSE KEY

3 Activate your license key

Bought a lifetime license? Activation is a quick one-time exchange: the panel sends us your Machine ID and the email you used at purchase, we send back your license key — then you paste it into the panel.




Settings → About & License → **Request license key**

1. **Request your key**
   Open **Settings** → **About & License** and click **Request license key**. A window shows your Machine ID.


2. **Send the request**
   Enter the **email you used at purchase** and click **Send activation request**. You'll receive your personal license key by email.

3. **Paste the key and Activate**
   In **Settings** → **About & License**, paste the key into the license key field and click **Activate**. No restart needed.

4. **Done**
   The panel unlocks and shows **Valid until...** and **Activated** in green. Trade on.



Before activation · **No license key entered**



After **Activate** · **Valid until...**

PREFER PROPERTIES?

Still works: right-click the chart → Indicators → FuseTrader_Pro → Properties → **00. License** → **License Key**, paste the key and click Apply.

REINSTALLING / NEW PC

Reinstalling NinjaTrader keeps the same Machine ID — your key still works. Only a new computer, a Windows reinstall or a rebuilt VM changes it. Moving to a new computer? Click **Remove license** in Settings → About & License on the old one, then click **Request license key** on the new computer and we'll reissue your key.


Futures trading involves substantial risk of loss. Past performance is not necessarily indicative of future results.

FREE TRIAL · 1 OF 3

Free 7-day trial


Want to try Fuse Trader Pro first? The **free 7-day trial** unlocks **every Pro feature** with one click — right here on your chart. No email, no license key, no card, no extra download.

Start the trial — three places



Settings → About & License

1. **The welcome window**
   Start 7-day Pro trial in the window shown once on a new computer (page 06).
2. **Settings → About & License**
   The green **Start 7-day Pro trial** button, shown while the trial is still available.
3. **A locked entry**
   Click a locked entry button — the welcome window opens with the same button.



The confirmation — it shows the exact end time and closes by itself

The rules

Length	7 days. It ends on day 7 at **17:00 US Eastern**; the start message shows the exact date and time.
One per computer	The trial can be started once per computer. It runs offline; changing the system clock does not restart or extend it.
All charts	Once started, the trial applies to Fuse Trader Pro on every chart of this computer.
Trial key	A trial license key (…_T7) you received earlier keeps working as before.

IMPORTANT · BEFORE YOU START


Fuse Trader Free and Fuse Trader Pro **cannot be in the same chart window** (also not on different tabs). Run the trial in a chart window without Free — page 11.

Futures trading involves substantial risk of loss. Past performance is not necessarily indicative of future results.


FREE TRIAL · 2 OF 3

During the trial

While the trial runs, the panel works exactly like a licensed Fuse Trader Pro. Two places show how much time is left.



Settings → About & License · **Trial: N days left**




The **TRIAL · Nd left** badge in the panel header


During a trial started with one click there is no **Remove license** button — there is no key to remove. **Request license key** stays available, so you can buy and request your lifetime key at any time.

Activating a paid key during the trial

Paste your paid license key in Settings → About & License and click **Activate** — the panel switches to the paid license and shows **Valid until…**. A paid key always takes precedence over a trial.



Remove license asks for confirmation



The trial continues after the paid key is removed

REMOVE LICENSE


Remove license (shown for a paid key) removes the key from this computer after you confirm. If your 7-day trial is still running, the panel goes back to it with the remaining time; otherwise it returns to **No license key entered**. You can activate again later with the same key. Removing a license never touches open positions.

Futures trading involves substantial risk of loss. Past performance is not necessarily indicative of future results.

FREE TRIAL · 3 OF 3

When the trial ends

Fuse Trader never cancels an order or closes a position when the trial ends — not at the deadline and not at restart. The panel stays on your chart, switches to **closing-only** and explains this in one message.




The trial-ended message

Disabled


New entries and adds: Buy/Sell Mkt, Bid/Ask, Click, Buy+ / Sell+ and click-to-place are greyed out ("Trial ended").

Still works

Closing and managing your open position and pending orders: Close 50%, Close All, cancel pending, dragging SL/PT, on-chart X and BE, Auto-BE, trailing and your risk locks.



About & License · **Trial ended**



The **TRIAL ENDED** badge
Simulated account. Any profit or loss shown is hypothetical.

THE MESSAGE

Get lifetime license opens the Fuse Trader card on **fuseindicators.com/#fuse-trader**, **Enter license key** opens Settings → About & License, **Close** closes it. Once you are flat, the panel stays with entries disabled, ready for a license key. Fuse Trader Free stays yours — it is a separate, free indicator.

Keep Pro after the trial

Get a lifetime license, then **Request license key**, paste the key and click **Activate** (page 07). Same Machine ID — no reinstall. Entries unlock right away.

Note: if you go back to a Fuse Trader Pro version older than 1.6 after starting a trial, that version treats the new trial record as damaged, so the trial counts as ended there.

Futures trading involves substantial risk of loss. Past performance is not necessarily indicative of future results.


FREE AND PRO

One edition per chart window

Fuse Trader Free and Fuse Trader Pro can both be installed and both can trade — but **each needs its own chart window**. They cannot be in the same chart window, **not even on different tabs** of it.

IMPORTANT · WHAT HAPPENS

The edition that comes second into a window does not create its panel there and shows a notice instead. Nothing in that window is changed — your orders and positions are not touched.



The notice in Fuse Trader Pro

What to do

1. **Remove Free from the window**
   Remove **Fuse Trader Free** from that chart window — from **all of its tabs**.
2. **Add Pro again**
   Add **FuseTrader_Pro** to the chart again (or use **Reload NinjaScript**).
3. **Or use another window**
   Leave Free where it is and put Fuse Trader Pro in a **different chart window**.



The right way: Fuse Trader Pro (left) and Fuse Trader Free (right) in two separate chart windows
Simulated account. Any profit or loss shown is hypothetical.


Futures trading involves substantial risk of loss. Past performance is not necessarily indicative of future results.

4

ORIENTATION


The panel at a glance

Two tabs — **Trading** for live execution, **Settings** for rules, brackets, display and license. Here's the Trading tab, top to bottom. A free trial adds a small **TRIAL** badge to the header strip.



Trading tab · managing an open trade
Simulated account. Any profit or loss shown is hypothetical.

1. **Trading Active**
   Master arm/disarm. Click it to lock: it turns red to **Trading Locked** and blocks all entries; click again to re-arm. It also turns red automatically when one of your risk rules is triggered.
2. **Position & Day P/L**
   Live status: FLAT or your open position, and the daily $ result.
3. **Active Locks · Auto Size**
   How many risk rules are armed, and the auto position-size toggle.
4. **Instrument & Account · Order Qty**
   What you trade, on which account, and your working quantity + quick chips.
5. **Bracket Preset**
   One-tap stop/target templates with a live risk & target readout.
6. **Entry**
   Buy/Sell at Market, Bid/Ask, or Click-to-place, with optional OCO.
7. **Stop Management**
   One-tap break-even, trailing, fixed SL and Auto-BE on profit.
8. **Manage**
   Close 50%, Close All, scale in (Buy+/Sell+), cancel pending.
9. **Bar Counter**
   Countdown to bar close.
10. **Ask / Spread / Bid**
    Live best bid and ask with sizes and the spread, right above the connection status; every row flashes on each update. Optional size columns in Settings → Display.



Trading Active → one click → Trading Locked · new entries are blocked until you unlock

Futures trading involves substantial risk of loss. Past performance is not necessarily indicative of future results.

5

EXECUTION

Order entry

Instrument & Account

The panel trades the instrument on the chart and the account selected here. Switch account (e.g. Sim101 → your funded account) from the dropdown — every button then routes there.

Order Qty

Set your working size with the – / + stepper, or tap a quick chip (defaults 1 · 2 · 3 · 5). Every entry button uses this quantity — unless Auto Position Size is on (page 19), which sets size for you from your risk.

Entry buttons

Buy / Sell Mkt	Market order — fills at the next available price.
Buy Bid / Sell Ask	A limit entry at the quoted price shown live on the button — the second-row execution option.
Buy Click / Sell Click	Arms click-to-place — your next click on the chart sets the order price.
OCO — cancel other on fill	When on, a filled entry auto-cancels the opposite resting order.

AUTO-BRACKET

With a Bracket Preset active (next page), every entry drops its stop and targets automatically at fill.

Dollar value in the previews

The **Click Buy / Click Sell** and Shift+click previews on the chart show the risk and target in dollars for the selected bracket preset and Order Qty (e.g. **2 Buy LMT 30086.75 | -100.00 $ / +50.00 $**). Nothing is added with preset None. The SL/PT drag preview always shows the dollar value, also when Display Unit is Ticks or Points.

Bar Counter

A live countdown to the current bar's close (e.g. **Bar 1m · 00:52**) — shows the time remaining until the current bar closes.

Futures trading involves substantial risk of loss. Past performance is not necessarily indicative of future results.

6

SETTINGS · BRACKET PRESETS


Bracket presets

A preset stores a stop-loss and up to three scale-out targets. Format on screen: **SL** = stop loss, and **T1 / T2 / T3** = targets, ticks × contracts. Select one and every entry attaches it automatically; the active preset is highlighted.

Scalp	SL 100t · T1 50t×1 — tight single-target scalp.
Runner 3	SL 100t · T1 50t×1 · T2 100t×1 · T3 150t×1 — scale out in three.
100/100	SL 100t · T1 100t×1 — symmetric 1:1.
150/150 · 200/200	Wider symmetric brackets for bigger swings.

READING A LINE

Runner 3 = stop 100 ticks, then take 1 contract at +50t, 1 at +100t, 1 at +150t — a built-in scale-out plan.




Settings · Bracket Presets

Editing — "Edit presets..."

Pick a slot (1–5), set a **Name** and **Stop-loss (ticks)**, then fill **T1 / T2 / T3** — each with its own Ticks (distance) and Contracts (how many to close there). Leave a row at 0/0 to skip it. **Save** to store.

Example shown: Preset 3 "100/100" — SL 100, T1 = 100 ticks × 1 contract, T2/T3 unused.



Edit dialog · preset slots 1–5


Futures trading involves substantial risk of loss. Past performance is not necessarily indicative of future results.

7

SETTINGS · STOP MANAGEMENT

Stop management & trailing

These values drive the one-tap **Stop Management** buttons on the Trading tab. Set them once here; the buttons then use these values.



Settings · Stop Management

- **Breakeven · BE 1 / 2 / 3**
  Tick offsets (1 / 5 / 20) behind the **BE +1 / +5 / +20** buttons — move stop to break-even plus that cushion.
- **Max loss stop (ticks)**
  200 — the fixed stop placed by the Trading-tab **SL** button. If the market is already beyond that price, the position is closed instead (page 16).
- **Tick trailing · Trail 1 / 2**
  10 / 30 ticks — the **TR +10 / +30** trailing buttons.
- **Bar trailing**
  Candles back (1) and **Offset** (2 ticks) — drive the **Bar** trail button.
- **Auto-BE · Manual / Fee Cover**
  Fee Cover adds a buffer so break-even also covers commissions: **Mini 1 tick**, **Micro 4 ticks**.

LIVE FROM YOUR PRESET

As the panel notes, Trigger & Offset are computed live from your active preset's T1 — so Auto-BE and trailing follow the bracket you're trading. Watch the live numbers on the Trading tab.

ON THE CHART

Stop and target lines are still draggable — grab a line to reprice; orders and panel update right away. The SL/TP handles themselves, plus the new on-chart **X** and **BE** controls, are covered on page 17.


Futures trading involves substantial risk of loss. Past performance is not necessarily indicative of future results.

7


SETTINGS · STOP MANAGEMENT · SAFETY

When a stop can't be placed

The **BE** and **SL** buttons replace your working stops with one new stop. If that price is already beyond the market, a stop there would trigger at once — so Fuse Trader protects the position instead of leaving it without a stop, and tells you what it did.



The safety pop-up
Simulated account.



Example: stop moved to the nearest valid price

- **Does not block trading**
  The pop-up sits over the chart, does not take keyboard focus and stays until you click **OK**. New messages are added to the same window (up to four).
- **Also logged**
  Each message is written to NinjaTrader's **Alerts Log** with a sound (Control Center → New → Alerts Log) and to the Log tab.
- **Auto-BE stays quiet**
  If no stop could be moved, Auto-BE simply tries again on the next tick — no pop-up.

What each message means

Position closed	Your new stop at X was already past the market, so it could not be placed. The position was closed to keep you protected.
Stop moved to X	The market moved past your requested stop while old stops were being cancelled. Your stop was placed at the nearest valid price instead.
Position closed	The broker rejected the new stop. The position was closed so it is not left without protection.
Check your position	Old stops were not cancelled within 5 seconds, so no new stop was sent. Your previous stops are still active.
Check your orders	Old target orders were not cancelled within 5 seconds. Check the chart for leftover target orders.

GOOD TO KNOW

Closing a position cancels all working orders on that instrument and account, and is a market order that can fill at a worse price in fast markets. These safety actions depend on your settings, platform, data and broker connection and may not execute as expected.

Futures trading involves substantial risk of loss. Past performance is not necessarily indicative of future results.

8

ON THE CHART · 1 OF 2

X & BE — on-chart controls

With a position open, Fuse Trader Pro draws two small square controls right next to NinjaTrader's native position label — **X** and **BE** — plus square, color-coded handles on your stop and target lines. No extra setup: they appear automatically the moment you're in a trade.



Open position on MNQ — native label, on-chart **X** / **BE**, and the square SL/TP handles
Simulated account. Any profit or loss shown is hypothetical.

X — flatten now

Cancels every working order and closes the position in one click. There is no confirmation dialog, so use it deliberately.

BE — move to breakeven

Moves your stop to the active Auto-BE offset — Manual value, or Fee Cover — the same values you set on the **Stop Management** page (page 15). If the market is already past that price, the position is closed instead (page 16).

SL/TP handles

Your stop and target lines carry square, color-coded handles with no outline. They position themselves automatically right behind NinjaTrader's native position label, wherever the chart puts it — there's nothing to configure, and the old SL/TP offset stepper is gone. Drag a handle to reprice; the order and panel update right away.

WHERE THEY SIT

X, BE and the SL/TP handles always sit right after the native position label — if you move or hide that label, they move with it.

Futures trading involves substantial risk of loss. Past performance is not necessarily indicative of future results.

8


ON THE CHART · 2 OF 2

Matching the chart colors

Fuse Trader Pro draws its own colored SL / PT / BE labels right on the chart — but NinjaTrader's own native order lines and price tags render underneath them too. Left at NinjaTrader's defaults, the two color systems compete for attention. This is the palette we use ourselves: Fuse's labels carry the meaning (red = risk, green = target, blue = breakeven); everything native stays a single neutral gray so it recedes into the background instead of fighting for attention.



Fuse's own SL / PT / BE boxes in color · native NinjaTrader lines and price tags in neutral gray
Simulated account (Market Replay). Any profit or loss shown is hypothetical.



Properties → Colors / Lines — the exact values, straight from the panel

WHY POSITION ENTRY PRICE IS DIFFERENT

It stays a distinct near-white (#C6C6C6) — it's your actual fill, the anchor everything else is measured from, so it shouldn't disappear into the background noise like a resting order does.


Futures trading involves substantial risk of loss. Past performance is not necessarily indicative of future results.

9

SETTINGS · AUTO POSITION SIZE

Auto Position Size

Instead of picking a contract count, tell the panel **how many dollars to risk per trade** — it sizes the position for you from your active preset's stop distance. Turn it on with the **Auto Size** toggle on the Trading tab.



Settings · Auto Position Size

- **Risk / Trade**
  Dollars you'll risk on the trade (e.g. $300). Size is derived from this and your stop.
- **Max Contracts**
  A ceiling you set for the calculated size (e.g. 10).

WORKED EXAMPLE · MNQ (TICK = $0.50)

Risk $300, preset stop 100 ticks → risk per contract = 100 × $0.50 = $50 → size = $300 ÷ $50 = **6 contracts** (within the Max Contracts cap). Wider stop → fewer contracts; tighter stop → more — your planned dollar risk stays the same. Example only. Actual results depend on fills, slippage and market conditions; a stop order may fill at a worse price than expected.

When Auto Size is off, the panel shows “manual Order Qty” and uses the size you set on the Trading tab. Tick value differs per instrument (NQ tick = $5, MNQ tick = $0.50).


Futures trading involves substantial risk of loss. Past performance is not necessarily indicative of future results.

10

SETTINGS · LOCKS · 1 OF 2

Locks & risk rules

Each rule arms independently; **Active Locks** on the Trading tab shows how many are on. These rules are designed to help you keep to the limits you set. They do not guarantee that a loss will be limited.



Settings · Locks

Trading lock HARD

Manual kill-switch — hard-locks trading. Turn it on whenever you want to stop trading for the session.

DCA lock

Blocks adding into a loss (no averaging down). **Max adds per trade** (3) caps how many add-ins are allowed.

Max daily loss

Per account. On hit (e.g. -$550): **flatten + lock** for the session. A limit you set.

Daily target

Realized only. On hit (e.g. +$1000): **flatten + lock** — trading stays locked after your daily target.

FLATTEN + LOCK

Max daily loss and Daily target don't just warn — they close positions and block new entries. Set them according to your own plan. Flatten orders are market orders and can fill at a worse price in fast markets.

Futures trading involves substantial risk of loss. Past performance is not necessarily indicative of future results.

10

SETTINGS · LOCKS · 2 OF 2

More locks & how they fire

Max contracts	Caps position size (MINI 0 = off). Blocks entries above the cap you set.
Trade loss limit	Per single trade (MINI). On hit (e.g. -$300, set via Amount ($)): flattens only that trade — does not lock the session.
Cooldown after hit	Enforced pause after a lock triggers — 15m · 1h · 2h · Session. Blocks new entries for the selected time.
Time window	Trade only inside your chosen range; entries outside are blocked.
US open lock	Blocks entries for X min after the open (e.g. 15).
Red news lock	Locks trading for X min around red news (e.g. 5) — blocks entries around high-impact news.

What happens when a lock fires

The green **Trading Active** banner turns red with the lock name and a countdown (e.g. “RED NEWS LOCK — 5 min left”) and the whole panel takes on a red tint. The buttons keep their colours, but new entries are blocked until the lock clears. A Cooldown extends the pause; the manual Trading lock holds until you release it or the session ends.



Red news lock active on MNQ.

EXAMPLE SETUP (NOT A RECOMMENDATION)

Max daily loss and **Daily target** set to your plan, **Trade loss limit**, a **Cooldown** and **DCA lock**. Choose values that match your own risk tolerance and your prop firm's rules.


Futures trading involves substantial risk of loss. Past performance is not necessarily indicative of future results.

11

SETTINGS · DISPLAY

Display & news

Under **Settings → Display** — tune what the panel draws on your chart, how risk is shown, and how news appears.



Settings · Display

Price Labels	Show entry / stop / target price labels on the bracket lines.
Watermark	Instrument / timeframe watermark on the chart background.
Price Line	Off · Right · Full — where the current-price line is drawn.
Ask/Bid size bars	Bar length follows live size at that price, next to the Ask/Spread/Bid strip. Off by default.
Display Unit	Currency · Ticks · Points — how risk & targets are shown. In Currency the position P&L shows two decimals (e.g. +305.50 $).
Bar Counter	Count Up — count elapsed instead of remaining.

News & latency

- **Alerts**
  Popup before red news (the lock itself is set under Locks).
- **Chart lines**
  Chart markers at news times.
- **Red news**
  Shows today's red-news list on the panel, no popup.
- **Latency**
  Footer pill: data-feed delay (PC UTC clock minus last tick), colored at 150 / 250 / 400 ms. Not a ping. Options: Display → Latency.

Pairs with the Red news lock (page 21): the list keeps events in view, the lock blocks new entries around them.



Today's red-news list on the Trading tab

ECONOMIC CALENDAR

The economic calendar is downloaded from a third-party economic calendar feed and refreshed by the panel when an internet connection is available. Event data may be delayed, incomplete or incorrect; do not rely on it as your only source of news.

SAVE IT ONCE

Set presets, locks, sizing and display, then save the chart as a template / workspace — every new chart opens with your saved settings.

Futures trading involves substantial risk of loss. Past performance is not necessarily indicative of future results.

YOU'RE SET

You're ready to trade

That's the whole panel. Import once, activate once (or start the free trial), then let the presets apply your brackets and the locks apply the rules you set.

Quick troubleshooting

Panel not in the list	Restart NinjaTrader once so compilation completes, then re-check Indicators → FuseSuite.
Still locked	Paste the license key into Settings → About & License (no extra spaces) and click Activate.
Key stopped working	You likely changed machines / reinstalled Windows. Click **Request license key** to send your new Machine ID for a fresh key. Moving on purpose? Use Remove license on the old computer first.
No panel, notice "Fuse Trader Free is already in this chart window"	**Important:** Free and Pro cannot be in the same chart window, not even on different tabs. Remove Free from that window (all of its tabs) and add Pro again (or Reload NinjaScript), or put Pro in another chart window (page 11).
No "Start 7-day Pro trial" button	The button is shown only while the trial is still available: no license is active and no trial was started on this computer before.
"Trial ended"	New entries are greyed out. Position management still works. Enter a lifetime license key in Settings → About & License (page 10).
Safety pop-up	"Position closed": BE or SL found the market already past the new stop, or the broker rejected it. "Check your position / orders": old orders did not cancel in time — check the chart (page 16).
P&L differs from the native Chart Trader	Turn on Properties → **99. Diagnostics** (off by default): while a position is open it writes a **[FUSE-DIAG]** line to the NinjaScript Output window every 2 seconds. Include it when you email support.
Entries don't go through	A risk-rule lock is active (red banner, red-tinted panel) — check the countdown in the banner and under Settings → Locks.

SUPPORT

Questions, a new Machine ID, or feedback? Email **fuseindicators@gmail.com** — you'll hear back from the trader who built it.

Futures trading involves substantial risk of loss. Past performance is not necessarily indicative of future results.

DISCLOSURES

Risk Disclosure

Risk Disclosure

Futures and forex trading contains substantial risk and is not for every investor. An investor could potentially lose all or more than the initial investment. Risk capital is money that can be lost without jeopardizing one's financial security or lifestyle. Only risk capital should be used for trading and only those with sufficient risk capital should consider trading. Past performance is not necessarily indicative of future results.

Fuse Trader Pro is a software tool for order execution and for applying risk rules you define. It does not provide trading advice or signals, does not guarantee profits and cannot prevent losses. Automated functions depend on your settings, platform, data and broker connection and market conditions, and may not execute as expected. You are solely responsible for your trading decisions and results.

Hypothetical Performance Disclosure

Screenshots in this guide that show profit or loss are from a simulated account. Any profit or loss shown is hypothetical. Hypothetical performance results have many inherent limitations, some of which are described below. No representation is being made that any account will or is likely to achieve profits or losses similar to those shown; in fact, there are frequently sharp differences between hypothetical performance results and the actual results subsequently achieved by any particular trading program. One of the limitations of hypothetical performance results is that they are generally prepared with the benefit of hindsight. In addition, hypothetical trading does not involve financial risk, and no hypothetical trading record can completely account for the impact of financial risk of actual trading. For example, the ability to withstand losses or to adhere to a particular trading program in spite of trading losses are material points which can also adversely affect actual trading results. There are numerous other factors related to the markets in general or to the implementation of any specific trading program which cannot be fully accounted for in the preparation of hypothetical performance results and all of which can adversely affect trading results.

Trademark

NinjaTrader® is a registered trademark of NinjaTrader Group, LLC. No NinjaTrader company has any affiliation with the owner, developer, or provider of the products or services described herein, or any interest, ownership or otherwise, in any such product or service, or endorses, recommends or approves any such product or service.